



# Merging the ETAP Library Update

Follow the procedure below to merge the library file update to your existing ETAP library.


1. Save a backup copy of your existing library file before proceeding with the merging.
2. Open your project file with ETAP 7.1.0.
3. From the Library menu on the menu bar, select Open.... Browse to the location of the library file 'LIB 7-5.lib' in your computer and then click **Open**.



This document is confidential and proprietary to Operation Technology, Inc. and may not be reproduced, published or disclosed to others without the written authorization of Operation Technology, Inc., 17 Goodyear, Suite 100, Irvine, CA 92618, USA. All Rights Reserved.





- ETAP will now load the LIB 7-5.lib. From the Library menu on the menu bar, select **Copy/Merge**.




This document is confidential and proprietary to Operation Technology, Inc. and may not be reproduced, published or disclosed to others without the written authorization of Operation Technology, Inc., 17 Goodyear, Suite 100, Irvine, CA 92618, USA. All Rights Reserved.

5. The Coy/Merge editor opens up. Ensure that the checkbox “Connect the project to the merged library” is checked, so that the project connects to the final merged library.
6. Now, browse to the location of the library file ‘etaplib700.lib’ or the destination library file of your choice in your computer by clicking on the File button in the bottom row. After selecting the destination library, click open.



This document is confidential and proprietary to Operation Technology, Inc. and may not be reproduced, published or disclosed to others without the written authorization of Operation Technology, Inc., 17 Goodyear, Suite 100, Irvine, CA 92618, USA. All Rights Reserved.

7. Click OK to continue with the merge process. A confirmation window giving a summary of the device libraries being merged (from source to destination library file) will appear.



8. Click **OK** to confirm and complete with the merge process.

This document is confidential and proprietary to Operation Technology, Inc. and may not be reproduced, published or disclosed to others without the written authorization of Operation Technology, Inc., 17 Goodyear, Suite 100, Irvine, CA 92618, USA. All Rights Reserved.